



Updated: November 25, 2021 **Document ID:** 217509

[Bias-Free Language](#)

Contents

Introduction

Prerequisites

- Requirements

- Components Used

Supported Paths

Comparison of Full Upgrade with Split Upgrade Method

- Sequence of Node Upgrade with Split Upgrade Method in a Distributed Deployment

- Sequence of Node Upgrade with Full Upgrade Method in a Distributed Deployment

- Advantages of Full Upgrade over Split Upgrade Method

Full Upgrade Flow

- Upgrade UI

- Welcome Page

- Checklist

- Prepare to Upgrade

- Upgrade Staging

- Upgrade Nodes

Summary

Health Checks

Post Upgrade Tasks

Issues and Remedies

Introduction

This document describes how to upgrade an existing ISE deployment from version 2.7 to 3.1 using the Full Upgrade method. It also includes how to use the Health Checks feature to detect and fix any potential deployment issues. The legacy method of upgrade is now termed as Split Upgrade and is available as an alternate option if the Full Upgrade method is not preferred.

By continuing to use our website, you acknowledge the use of cookies.

[Privacy Statement](#) > [Change Settings](#) >

Requirements

Cisco recommends that you have knowledge of these topics:

- Identity Services Engine (ISE)
- Understanding of terminology used to describe different types of ISE deployments

Components Used

The information in this document is based on these software and hardware versions:

- ISE, Release 2.7, patch 4
- ISE, Release 3.1

The information in this document was created from the devices in a specific lab environment. All of the devices used in this document started with a cleared (default) configuration. If your network is live, ensure that you understand the potential impact of any command.

Note: The procedure is similar or identical to other ISE versions. These steps can be used on 2.6 and above to upgrade to 3.1 and above ISE Software Releases unless stated otherwise.

Supported Paths

Full upgrade to ISE 3.1 is supported from

- ISE 2.6 patch 10 and above
- ISE 2.7 patch 4 and above
- ISE 3.0 patch 3 and above

Split upgrade to ISE 3.1 is supported from ISE 2.6 and above versions, with or without any patch.


Comparison of Full Upgrade with Split Upgrade Method

By continuing to use our website, you acknowledge the use of cookies.

[Privacy Statement](#) > [Change Settings](#) >

Sequence of Node Upgrade with Split Upgrade Method in a Distributed Deployment

Requires a minimum of 5 steps for a fully distributed deployment to upgrade to the newer version.




Considering approximate 240 minutes for each step, the total upgrade process here would take 240×5 minutes = 20 hours.

By continuing to use our website, you acknowledge the use of cookies.

[Privacy Statement](#) > [Change Settings](#) >

Sequence of Node Upgrade with Full Upgrade Method in a Distributed Deployment

Requires only 2 steps for a fully distributed deployment to upgrade to the newer version.



Again, considering approximate 240 minutes for each step, the total upgrade process is now reduced to 240*2 minutes = 8 hours.

By continuing to use our website, you acknowledge the use of cookies.

[Privacy Statement >](#) [Change Settings >](#)

are upgraded in
on of the

- The Full Upgrade method is hassle-free in terms of upgrade sequence as there are just 2 steps. The Split Upgrade method requires the nodes to be sequenced appropriately before starting the upgrade process.
- The Full Upgrade method retains the roles and personas as it was prior to the upgrade. The Split Upgrade method switches the primary and secondary admin roles in the upgraded version.
- The points of failures have been reduced in the Full Upgrade method by eliminating the API dependency with deployment-related changes during the upgrade process.
- The Full Upgrade method allows to track the upgrade status from the secondary admin node when the primary admin node goes down for an upgrade. This is not possible in the Split Upgrade method.
- Patch installation post-upgrade is automated and is provided as an option in the Full Upgrade method.

Caution: Full upgrade requires a complete downtime because all the PSNs go down for upgrade at the same time. Ensure that the activity is planned during a scheduled maintenance window.

Full Upgrade Flow

This document demonstrates the upgrade flow of a 4 node deployment. The overall process remains the same for two-node or other multi-node deployments.

The screenshot displays the Cisco Identity Services Engine (ISE) Administration console. The top navigation bar includes 'Home', 'Context Visibility', 'Operations', 'Policy', 'Administration', and 'Work Centers'. A 'License Warning' icon is visible in the top right. The breadcrumb trail shows: System > Identity Management > Network Resources > Device Portal Management > pxGrid Services > Feed Service > Threat Centric NAC. The main navigation menu includes: Deployment, Licensing, Certificates, Logging, Maintenance, Upgrade, Health Checks, Backup & Restore, Admin Access, and Settings. A yellow box highlights a link: 'Click here to do wireless setup Do not show this again'.

The 'Deployment' section is active, showing a tree view with 'Deployment' and 'PAN Failover'. The 'Deployment Nodes' table is displayed with the following data:


Hostname	Personas	Role(s)	Services	Node Status
<input type="checkbox"/> cisco-ise-1	Administration, Monitoring	PRI(A), SEC(M)	NONE	✓
<input type="checkbox"/> cisco-ise-2	Administration, Monitoring	SEC(A), PRI(M)	NONE	✓
<input type="checkbox"/> cisco-ise-3	Policy Service		ALL	✓
<input type="checkbox"/> cisco-ise-4	Policy Service, pxGrid		SESSION,PROFILER,DEVICE ADMIN	✓

By continuing to use our website, you acknowledge the use of cookies.

[Privacy Statement >](#) [Change Settings >](#)

Upgrade UI

Navigate to **Administration > System > Upgrade** in order to begin the activity as shown in the image.



Upgrade Selection

Select the upgrade process you want to carry out:

1. Full upgrade is a multi-step process that enables a complete upgrade of your Cisco ISE Deployment. This will upgrade all nodes in parallel so services will be down during the upgrade with this option. This is intended to upgrade the deployment as quickly as possible.
2. Split upgrade is a multi-step process that enables the upgrade of your Cisco ISE Deployment while allowing services to remain available during the upgrade process for end-users and administrators. This may require changes to the network or load balancers to ensure there are available nodes to service authentications. Uptime is accomplished by upgrading nodes in batches and is the option to limit downtime while taking longer than full upgrade.


Before you begin an upgrade process, check that all your Cisco ISE software is stable by performing the required [Health Checks](#).

- Full Upgrade
- Split Upgrade

Start Upgrade

Note: Only the Split Upgrade method is supported on ISE 2.6 patch 9 and below, ISE 2.7 patch 3 and below, and ISE 3.0 patch 2 and below. By default, the Split Upgrade window is launched for these versions. The Split Upgrade process can be referred from [here](#). Select the **Full Upgrade** radio button and click **Start Upgrade**.

Welcome Page



By continuing to use our website, you acknowledge the use of cookies.

[Privacy Statement >](#) [Change Settings >](#)

Checklist

Review the checklist and ensure to complete the tasks before you proceed further.

The screenshot displays the Cisco Identity Services Engine (ISE) Upgrade Checklist page. The navigation menu includes Home, Context Visibility, Operations, Policy, Administration, and Work Centers. The 'Administration' menu is expanded, showing System, Identity Management, Network Resources, Device Portal Management, pxGrid Services, Feed Service, and Threat Centric NAC. The 'Upgrade' page is active, showing a progress bar with steps: 1 Welcome, 2 Checklist (current), 3 Prepare to Upgrade, 4 Upgrade Staging, 5 Upgrade Nodes, and 6 Summary. The checklist includes tasks under the following categories:

- Backup ISE**
 - Configuration and operational data (Administration > System > Backup & Restore)
 - Backup system logs (Operations > Troubleshoot > Download Logs)
 - Export certificates and private keys (Administration > System > Certificates > System Certificates)
- Software**
 - Review the ISE Upgrade Guide and Release Notes for upgrade information (<http://cisco.com/go/ise>)
 - Confirm valid ISE upgrade paths. Ensure that a repository is available to store the ISE upgrade bundle (Administration > System > Maintenance > Repository)
 - Download the ISE upgrade bundle and place it in the repository (ISE software is available at <http://cisco.com/go/ise>)
- Credentials**
 - Make a note of the Active Directory join credentials, and the RSA SecurID node secret, if applicable.
- Operational Data Purge**
 - Purge operational data to improve upgrade performance (Administration > System > Maintenance > Operational Data Purge)
- License**
 - Convert your old licenses to the new license types through the Cisco Smart Software Manager (CSSM).
 - Enable the new licenses in the Administration > System > Licensing window. Check the checkboxes for all your purchased licenses, and click Enable.

A checkbox labeled "I have reviewed the checklist" is checked. A "Print Checklist" button is located below the checklist. At the bottom right, there are "Back" and "Next" buttons.

Tick the checkbox that states **I have reviewed the checklist** and click **Next**.

Prepare to Upgrade

A pre-check is run on the complete deployment prior to the upgrade and the results are displayed on this page. Apart from the checks, at this step the upgrade bundle is downloaded on all the nodes, offline data

By continuing to use our website, you acknowledge the use of cookies.

[Privacy Statement](#) > [Change Settings](#) >


upgrade (ODU) is run on the secondary admin node (this is analogous to the Upgrade Readiness Tool (URT) simulation of the Split Upgrade method) and finally, it also displays the time estimate for the activity.

Upgrade bundle is to be downloaded from the [Cisco Software Download page](#).

Upgrade bundle for upgrading ISE version 2.6, 2.7, 3.0 to 3.1. This is a signed bundle for image integrity.
 ise-upgradebundle-2.6.x-3.0.x-to-3.1.0.518.SPA.x86_64.tar.gz
[Advisories](#)

In order to run the pre-upgrade check, select the Repository name in which the upgrade bundle is placed. Select the upgrade bundle file name from the Bundle dropdown box.

Note: Full Upgrade method also introduces automatic patch installation post-upgrade. The patch file is to be placed in the same repository along with the upgrade bundle and the patch file name can be selected from the dropdown if automatic patch installation is desired.



Upgrade

[Home](#)
[2 Checklist](#)
[3 Prepare to Upgrade](#)
[4 Upgrade Staging](#)
[5 Upgrade Nodes](#)
[6 Summary](#)

Prepare to Upgrade

From the following drop-down lists, choose the required repository, upgrade software bundle, and patch file. Then, click Start Preparation.

Repository*

Bundle*

Patch

[Start Preparation](#)

Click on **Start Preparation** in order to start running the pre-checks. All the prechecks, except the Bundle Download and Configuration Data Upgrade check expire automatically after 4 hours of initiating the system

By continuing to use our website, you acknowledge the use of cookies.

[Privacy Statement](#) > [Change Settings](#) >

validation. Configuration Data Upgrade, which is nothing but the ODU, expires after 12 hours.

The screenshot shows the Cisco Identity Services Engine (ISE) Administration console. The 'Upgrade' tab is selected, and the 'Estimated time of upgrade process' is 5hr 15min. The progress bar shows the following steps:

- Repository Validation: 4/9 (Green)
- Bundle Download: 4/9 (Green)
- Memory Check: 4/9 (Green)
- PKI Failover Validation: 0/3 (Green)
- Scheduled Backup Check: 0/3 (Blue)
- Config Backup Check: 0/3 (Blue)
- Configuration Data Upgrade: 0/3 (Green)
- Platform Support Check: 4/9 (Green)
- Deployment Validation: 0/3 (Green)
- DNS Resolvability: 4/9 (Green)
- Trust Store Certificate Validation: 0/3 (Green)
- System Certificate Validation: 4/9 (Green)
- Disk Space Check: 4/9 (Green)
- NTP Resolvability and Time Source Check: 4/9 (Green)
- Leaf Average Check: 4/9 (Green)
- License Validation: 0/3 (Orange)
- Services or Process Failures: 4/9 (Green)

Buttons for 'Download Report' and 'Refresh Failed Checks' are visible. At the bottom right, there are 'Back' and 'Start Staging' buttons.

Note: PAN failover setting should be disabled before upgrade activity. If not done manually, it gets automatically disabled once the upgrade is triggered.

Note: ISE 3.0 and above mandates the use of Smart Licensing. It does not support Traditional Licensing. In case Smart Licensing is not enabled or registered prior to the upgrade, ISE lands on Smart Licensing Evaluation period by default post-upgrade. License Migration reference link: [Products - ISE Licensing Migration Guide - Cisco](#). When you upgrade ISE from 2. x to 3.x, it involves licensing tier changes. Details available here: [Cisco Identity Services Engine - Cisco ISE License FAQ - Cisco](#).

Caution: All types of configuration changes on ISE are to be avoided once the Configuration Data Upgrade is triggered. Any changes made would be lost after the upgrade.

If any of the component pre-checks fail, they are displayed in red or orange colour based on their criticality. The failures highlighted in red need to be mandatorily rectified before proceeding further. The warnings highlighted in orange will not stop the upgrade process, however, it is good to fix them as best practice and to avoid impacting the deployment features and functionalities in future.

Once the errors are rectified, click on Start Staging to proceed further.

Upgrade Staging


During upgrade staging, the upgraded database file is copied to all the nodes in the deployment and the configuration files are backed up on all nodes of the deployment.

By continuing to use our website, you acknowledge the use of cookies.

[Privacy Statement](#) > [Change Settings](#) >

in this step, the
/DNS


configuration. All other nodes also create these files but need to additionally copy the dump file from the secondary admin node.



Click **Next** when the staging completes for all the nodes.

Upgrade Nodes

Click on **Start** in order to trigger the upgrade.



A pop-up message confirms that the upgrade is triggered and all the nodes are displayed in a queue with the

By continuing to use our website, you acknowledge the use of cookies.

[Privacy Statement >](#) [Change Settings >](#)

Administration > System > Upgrade on the secondary admin node's GUI in order to continue viewing the status.

Upgrade

[Home](#) [Upgrade Nodes](#)

Upgrading Nodes

View the progress of the upgrade process on each Cisco ISE node.

Upgrade progress can be monitored from Secondary PAN UI while Primary PAN is getting upgraded and from Primary PAN UI while Secondary PAN is getting upgraded.

Estimated time of Upgrade process: **5hr 12min**

Overall Upgrade Progress

4hr 45min



Once the primary admin node gets upgraded and the services come up, the system logs out of the secondary admin node's GUI. Users can now switch back to monitoring the status from the primary admin

By continuing to use our website, you acknowledge the use of cookies.

[Privacy Statement](#) > [Change Settings](#) >

node's GUI while all the other nodes of the deployment go down for the upgrade simultaneously.

The screenshot shows the Cisco ISE Upgrade Wizard interface. At the top, there is a navigation menu with tabs: Deployment, Licensing, Certificates, Logging, Maintenance, Upgrade (selected), Health Checks, Backup & Restore, Admin Access, and Settings. Below the menu is a progress bar with six steps: Welcome, Checklist, Prepare to Upgrade, Upgrade Staging, Upgrade Nodes (5), and Summary (6). The 'Upgrade Nodes' step is currently active. Below the progress bar, the estimated time of the upgrade process is 5hr 12min. A section titled 'Overall Upgrade Progress' shows a progress bar at 2hr 34min. Below this, four nodes are listed: cisco-ise-1.gce.iselab.local, cisco-ise-2.gce.iselab.local, cisco-ise-3.gce.iselab.local, and cisco-ise-4.gce.iselab.local. Each node has a progress bar and a status icon. The first node is green, while the others are blue. A box for the second node shows 'STEP 2 OF 8 - VERIFY FILES IN BUNDLE'. At the bottom left, there is an 'Exit Wizard' button.

Once all the nodes get upgraded successfully, the status will change to green colour.

The screenshot shows the Cisco ISE Upgrade Wizard interface after the upgrade is complete. The navigation menu is the same. The progress bar now shows all six steps completed: Welcome, Checklist, Prepare to Upgrade, Upgrade Staging, Upgrade Nodes (5), and Summary (6). The estimated time of the upgrade process is 0hr 15min. The 'Overall Upgrade Progress' bar is now green and shows 0hr 15min. Below this, the four nodes are listed: cisco-ise-1.gce.iselab.local, cisco-ise-2.gce.iselab.local, cisco-ise-3.gce.iselab.local, and cisco-ise-4.gce.iselab.local. All nodes now have green progress bars and status icons, indicating successful completion.

By continuing to use our website, you acknowledge the use of cookies.

[Privacy Statement](#) > [Change Settings](#) >

[Back](#) [Next](#)

If there are any failed nodes, a pop-up window with information about the failed node is displayed. Click **OK** in the popup window to de-register the failed nodes from the deployment. These have to be individually upgraded/re-imaged and joined back to the deployment if any.

Click **Next** in order to view the overall upgrade summary reports.

Summary

After the upgrade process is complete, the diagnostic upgrade reports for the deployment can be viewed and downloaded from this page.

Cisco ISE Administration - System Evaluation Mode 89 Days

Deployment Licensing Certificates Logging Maintenance **Upgrade** Health Checks Backup & Restore Admin Access Settings

Welcome Checklist Prepare to Upgrade Upgrade Staging Upgrade Nodes **Summary**

Summary

You are successfully completed Upgrade workflow! Download all reports before clicking Finish.

Checklist [Print Checklist](#)

Prepare to Upgrade [Download Report](#)

Upgrade Report [Download Report](#)

System Health [Download Report](#)

[Exit Wizard](#) [Finish](#)

Health Checks


In order to validate the deployment status post-upgrade, a health check runs automatically to verify the deployment's status. This report can be downloaded from the Summary page of the upgrade flow. If an on-demand health check is required at any point in time, navigate to **Administration > System > Health Checks** and click on **Start Health Checks**.

By continuing to use our website, you acknowledge the use of cookies.

[Privacy Statement >](#) [Change Settings >](#)

Health Checks

Validate your deployment against any critical errors. Starting will perform a range of checks to ensure that all your software is working stable (Health Check might not respond for 15 minutes). Once validation will finish you can download report. After successful checking you can go to [Upgrade Workflow](#).



Health Checks completed. You can go to Upgrade Workflow.


[Download report](#)

Post Upgrade Tasks

When a user logs in to the primary admin node's GUI after you complete the upgrade, a pop-up message is displayed regarding post-upgrade tasks.

By continuing to use our website, you acknowledge the use of cookies.

[Privacy Statement](#) > [Change Settings](#) >



Click the post-upgrade tasks hyperlink on the pop-up message in order to review the task details and complete them.

Issues and Remedies

1. If the primary admin node upgrade fails, promote the secondary admin to the primary admin and then re-try the upgrade.
2. If the upgrade fails on any other node apart from primary admin, the node would have to be deregistered from the deployment. This node will have to be upgraded individually or reimaged directly to the upgraded version and can be joined back to the deployment.

Revision History

Revision	Publish Date	Comments
3.0	17-Nov-2021	Formatting edits.
2.0	30-Oct-2021	Initial Release
1.0	30-Oct-2021	Initial Release

Quick Links

[About Cisco](#)

[Contact Us](#)

[Careers](#)

[Connect with a partner](#)

By continuing to use our website, you acknowledge the use of cookies.

[Privacy Statement >](#) [Change Settings >](#)

[Feedback](#)

[Help](#)

[Terms & Conditions](#)

[Privacy Statement](#)

[Cookies](#)

[Accessibility](#)

[Trademarks](#)

[Supply Chain Transparency](#)

[Newsroom](#)

[Sitemap](#)



©2023 Cisco Systems, Inc.

By continuing to use our website, you acknowledge the use of cookies.

[Privacy Statement >](#) [Change Settings >](#)