

Deployment Guide for VMware vSphere

Virtual Multimedia Resource Function

Installation Instructions

Copyright

© Ericsson AB 2016–2018. All rights reserved. No part of this document may be reproduced in any form without the written permission of the copyright owner.

Disclaimer

The contents of this document are subject to revision without notice due to continued progress in methodology, design and manufacturing. Ericsson shall have no liability for any error or damage of any kind resulting from the use of this document.



Contents

1	About This Document	1
2	vMRF Deployment Principles for VMware	2
3	vMRF Deployment Process for VMware	3
4	Prerequisites for vMRF Deployment	6
4.1	Download and Extract vMRF Software Delivery Package	6
4.2	Prerequisite for Future Deployments	6
5	vMRF Deployment Preparations for the Cloud Administrator	7
5.1	Prepare and Configure Cloud Hardware and Software	7
5.2	Create Network Topology	7
6	vMRF Deployment for the End User	9
6.1	Initial VNF Configuration Data for Deployment	9
6.2	Deploy the OVF Template	9
6.3	Power On vMRF vApp	12
6.4	Check vMRF Status	12





1 About This Document

This document describes vMRF deployment on a VMware cloud service. VMware service means VMware vSphere® including VMware ESXi® and VMware vCenter Server®.

The following user roles are distinguished in this document:

End User

The end user is the vMRF operator and deployment responsible, who is assumed to be a cloud service consumer on a vSphere cloud service. The end user is also referred to as a tenant.

Cloud Administrator

The cloud administrator is the cloud service provider who delivers the cloud service to the end user. The cloud administrator must fulfill certain prerequisites before the end user can start deploying vMRF.

2 vMRF Deployment Principles for VMware

If the hardware and software requirements are met, and after the needed configurations in VMware are done, vMRF is instantiated.

vMRF can contain one or more Virtual Network Functions (VNF).

A single VNF contains multiple Virtual Machines (VMs). See [Figure 1](#) for an example overview of deployment with two VNFs.




Figure 1 vMRF Deployment



3 vMRF Deployment Process for VMware

The vMRF deployment process consists of preparations and basic configuration of the cloud environment, and the actual instantiation of one or more vMRF VNF instances.




Figure 2 vMRF Deployment Process

1. Prepare the cloud environment to run vMRF

This set of steps is done by the cloud administrator.

a. Prepare and configure cloud hardware and software

This step involves checking that the necessary hardware exists, and making hardware-related configuration in VMware and in the host Operating System so that the requirements listed in [Prerequisites for vMRF Deployment](#) on page 6 are fulfilled.



b. Create the network topology

This step involves ensuring that the required networks to which the VNF connects are in place.

2. Deploy and check vMRF

This set of steps is done by the end user.

a. Download and extract the vMRF software delivery package

The vMRF software delivery package contains the Open Virtualization Format (OVF) template and the related files. The vMRF software delivery package must be extracted to a place where the files can be accessed by vSphere. vSphere offers the following options:

- A local directory that is accessible by the vSphere client
- The files can be uploaded to an HTTP server connected to the vCenter

b. Deploy OVF Template

The extracted OVF template must be deployed in VMware, which means that the VMs and related resources in the OVF template become visible in the inventory. This step is repeated for each VNF that needs to be created.

During OVF template deployment, cloud configuration data must be provided for the VNF. At the same time, initial configuration data can also be provided for the VNF. This makes it possible for the VNF to have all necessary configuration for processing traffic right after being created.

Note: If initial configuration data is not imported during OVF template deployment, it must be performed after power-on. For more information, refer to the [Initial Configuration Guide](#).

c. Provide Initial Configuration and Cloud Configuration Data

Initial configuration data means the data needed for vMRF to start processing traffic. It can either be provided during deployment in Base64 encoding, or imported in an `.iso` file.

If you are importing this initial configuration data during deployment, you must prepare it so that it matches your environment.

For other options, refer to [Initial Configuration Guide](#).

d. Power On vMRF vApp

After powering on the vMRF vApp, vMRF starts running traffic. This step is repeated for each VNF instance that needs to be created.



e. Check vMRF status

It is recommended to run a status check on the newly deployed vMRF.



4 Prerequisites for vMRF Deployment

Before the end user can deploy and use vMRF, the cloud administrator must ensure that the environment fulfills hardware, software, and network requirements. The main requirements are listed in [vMRF Infrastructure Requirements](#).

4.1 Download and Extract vMRF Software Delivery Package

Before the deployment, the end user must download and extract the vMRF software delivery package. Both the end user and the cloud administrator must have access to the proper example files in the package.

Steps

1. Download the vMRF software delivery package to a computer from which the cloud service clients are reachable.
2. Extract the vMRF software delivery package.
3. Check that the following files exist after extracting the vMRF software delivery package:
 - Deployment files (.ovf files)

OVF File Name	Description
vmrf.ovf	OVF file for deployment with platform automatic IP address allocation from a predefined IP address pool.
vmrf_man_ip.ovf	OVF file for deployment with manual IP address allocation.

- vMRF image (.vmdk file)

4.2 Prerequisite for Future Deployments

The VMware vSphere Content Library is recommended to be available to store the deployed vMRF VNF vApp as a template. The vApp template can be used to deploy new instances of the same version of the VNF quickly and in a consistent way.



5 vMRF Deployment Preparations for the Cloud Administrator

The procedures for vMRF deployment preparation must be performed by the cloud administrator to prepare the cloud environment for running vMRF. The procedures described in this section serve as examples only to demonstrate how to fulfill the vMRF requirements.

5.1 Prepare and Configure Cloud Hardware and Software

Preparation for vMRF deployment starts by checking that the necessary hardware exists, and making hardware-related configurations in VMware, in the hypervisor, and in the host Operating System.

5.1.1 Group Compute Nodes for vMRF into DRS Cluster

Perform this procedure only if you want to specify exactly which hosts can run vMRF due to, for example hardware considerations.

Steps

1. Create a Distributed Resource Scheduler (DRS) cluster for the hosts selected to run vMRF. For the details, refer to [Using DRS Clusters to Manage Resources](#) in the VMware documentation.
2. Use VM-Host affinity rules to define a relationship between vMRF VMs and the group of hosts selected to run vMRF. For the details, refer to [VM-Host Affinity Rules](#) in the VMware documentation.

5.2 Create Network Topology

The vMRF VNF instance connects to networks. The networks in [Table 1](#) must be created already before the VNF instance can be deployed, since the OVF template uses them as input parameters.

Table 1 vMRF Networks

Network Type
VNF-internal ⁽¹⁾
H.248 signaling towards MTAS
User plane towards media networks
Network reserved for future use



- (1) Each VNF instance version requires a dedicated VNF-internal network.

Steps

1. Using the network plan, create the required networks listed in [Table 1](#), if they do not exist, and configure distributed port group parameter **VLAN type** in the vSphere Web Client.

- For access vNIC setup, select **VLAN** and configure **VLAN ID**.

Note: The corresponding **VLAN ID** values must also be given in vMRF network level configuration data.

2. Create network protocol profiles and associate them with the networks created in [Step 1](#).

Depending on the IP allocation alternative, the following additional configuration options apply:

- `vmrf.ovf`: network protocol profiles must be configured with IP pool, subnet, subnet mask, and gateway, and associated to the networks in [Table 1](#).
- `vmrf_man_ip.ovf`: network protocol profiles can be configured with subnet, subnet mask, and gateway, and associated to the networks in [Table 1](#), or the information is provided during deployment.

In the case of manual IP address allocation, the use of network protocol profiles is mandatory if vSphere 6.5 is used, since vCenter 6.5 does not render prompting of subnet information properly during deployment.

3. Inform the personnel who are doing the vMRF deployment.



6 vMRF Deployment for the End User

After the deployment preparations are completed by the cloud administrator, the end user can start vMRF deployment.

6.1 Initial VNF Configuration Data for Deployment

Initial configuration data means the data needed for vMRF to start processing traffic. This procedure describes how to prepare initial configuration data if you are importing it during deployment. For other options, refer to [Initial Configuration Guide](#).

While providing cloud configuration data during deployment is mandatory, importing initial configuration is optional. It can be provided during deployment in Base64 encoding. The input can be generated with the following command:

```
base64 -w 0 mrsvconfig.tar.gz
```

If the size of the initial configuration data file `mrsvconfig.tar.gz` exceeds the 23 kB limit, it can be imported in an `.iso` file. For more information, see [Create VNF Configuration ISO File](#) on page 9.

6.1.1 Create VNF Configuration ISO File

Initial configuration data must be imported to the VNF in an `.iso` if it exceeds the limit imposed by vSphere and cannot be provided during deployment with cloud configuration data.

Steps

1. Rename the `exported_config.tar.gz` file to `mrsvconfig.tar.gz`.
2. Create an `.iso` file which includes the `mrsvconfig.tar.gz` file. For example, on a Linux computer, use the following command:

```
genisoimage -l -iso-level 4 -o mrs-init.iso mrsvconfig.tar.gz
```

6.2 Deploy the OVF Template

This procedure describes how to upload the vMRF VMs to the VMware vSphere inventory by deploying the vMRF OVF template.

Steps

1. Deploy the OVF template based on the instructions in the VMware documentation for the [vSphere web client](#). For the deployment options, use the following information:



- a. For IP allocation, depending on the IP address allocation method, select one of the following OVF files:

OVF File Name	Description
vmrf.ovf	OVF file for deployment with platform automatic IP address allocation from a predefined IP address pool.
vmrf_man_ip.ovf	OVF file for deployment with manual IP address allocation.

- b. For destination network mapping, use the information from [Create Network Topology](#) on page 7.
- c. Based on the IP address allocation method chosen for the deployment, provide the following information as a minimum in the interactive window:

For manual IP address allocation, provide the following vApp properties:

vApp Property Type	vApp Property
Emergency user credentials	Username
	Password hash
	Ssh public key
O&M IP address of the VNF	Movable IP address, an IPv4 address in dot-decimal notation
NTP server IP address	NTP IPs, that is, the list of NTP server addresses separated by a space character
Shared storage configuration	Shared storage server username
	Shared storage server path
	Shared storage server IP
	Shared storage server port
	Shared storage server fingerprint
	Shared storage ssh private key
Announcement storage configuration	Announcement storage server username
	Announcement storage server path
	Announcement storage server IP



vApp Property Type	vApp Property
	Announcement storage server port
	Announcement shared storage server fingerprint
	Announcement storage ssh private key
IPv4 or IPv6, or both type of addresses for media networks	Media IPv4 address
	Media IPv6 address
	Trusted IPv4 address
	Trusted IPv6 address
IPv4 addresses for the following networks: VNF-internal, O&M, signaling, and li	Internal IP address
	Management IP address
	Signaling IP address
	LI IP address
Media network subnet information	Media IPv4 Subnet mask
	Media IPv6 Subnet mask
	LI Subnet mask
	Trusted IPv6 Subnet mask
Initial configuration (optional)	Initial configuration
Gateways and subnet network properties to all networks, if network profiles are not associated ⁽¹⁾	Netmask
	Gateway

(1) The vCenter 6.5 deployment wizard shows property fields for **Gateway** and **Netmask** under section **Networking Properties** on the **Customize template** step. These are related to the vCenter 6.5 rendering problem, and can be left empty.

Result: The vMRF vApp with one VM becomes visible in the inventory.

- For possible future vMRF VNF deployments, create a vApp template from the vMRF vApp and add the vApp template to the Content Library. For more information about the Content Library, refer to the [VMware documentation](#).
- If initial configuration is going to be provided during deployment and it has not already been provided in Base64 encoding, upload the .iso file created in [Create VNF Configuration ISO File](#) on page 9. Otherwise continue with [Step 5](#).

Note: This step is optional.

- Mount the .iso file on the VM as a CD/DVD image in the vApp.



5. Create a VM template from the VM. Add the VM template to the Content Library, for manual scaling.

Note: Cloning a VM template to the Content Library from a VM deployed with automatic IP address allocation disrupts the property types referring to network properties. Therefore, the property types must be corrected after manual scaling of the VM before power-on.

6.3 Power On vMRF vApp

This procedure describes how to power on the vMRF vApp that is now in the inventory. After powering on the vMRF vApp, vMRF starts running traffic.

Steps

1. Navigate to the VM in the vMRF vApp.
2. Right-click the VM and select **Power On**.

If a delay is set in the startup settings of the VM, the VM is powered on only after the set length of time.
3. Check that the VM works correctly as described in [Check vMRF Status](#) on page 12.
4. Use the VM template created in [Step 5 in Section 6.2](#) to deploy the required number of VMs.
5. If manual IP address allocation is chosen, modify VM properties so that each VM has unique IP addresses.
6. Power on all the newly created VMs and continue with [Check vMRF Status](#) on page 12 to verify the whole VNF.

6.4 Check vMRF Status

This procedure describes how to verify the vMRF deployment. The status check involves running a vMRF command.

Steps

1. Open an SSH connection to the O&M IP address of the vMRF VNF instance using the following command:

```
ssh -A <user_ID>@<O&M_IP_address>
```

2. Run the following command to check the status of VMs in the cluster:

```
verify_vmrf_cluster_status.py
```



- If the VMs are operating correctly, the OK status is displayed in the command printout. You can exit this procedure.
 - If there are VMs with faulty components, a list of faulty VMs and detailed component information of the cluster is displayed. Continue with the next step.
3. Check all components with erroneous state. For specific trouble cases and remedies, refer to the [vMRF Troubleshooting Guideline](#).

Note: The `MrfDirector` and `COM` components are in the OK state only for the VM whose `SC` role is `ACTIVE`, that is, the active System Controller (SC) VM. In all other VMs, these components are in the `OK, NOT RUNNING` state, which is normal behavior.